Table of Contents

2025/07/01 20:50

Configuring a Static IP Address	1
Configuring Static IP Addresses Via The FreeNAS GUI	1
Configuring Static IP Addresses Using The FreeNAS Console Setup	3

Configuring a Static IP Address

So far we have relied upon the DHCP server built into the router to assign IP addresses to the NICs in the server. This is inconvenient for reasons already outlined.

So let us assign static IP addresses to these NICs. This will ensure that the FreeNAS web GUI IP address will no longer change. This is much more expedient when administering a server.

Make sure it is outside of the range of the DHCP server.

There are two ways to do this. You can do it via the FreeNAS web GUI. This is the preferred method in most cases.

The other way is via the console, either directly at the server with a keyboard and monitor, or using an IPMI remote console viewer. This worked for me.

I have included both methods in the guide so you can see which works best for you.

Configuring Static IP Addresses Via The FreeNAS GUI

Account	System	Tasks	Network	Storage	Directory	Sharing	Services	Plugins	Jails R	eporting	T Wizard
System											
Information	General	Boot	Advanced	Email	System Data	aset Tunable	s Update	CAs	Certificates	Support	
System I	nformatio	n									
Hostname	2	E	dit								
Build	FreeN	AS-9.10-R	ELEASE (2def	9c8)							
Platform	Intel(R) Xeon(R)	CPU E5-2620	v3 @ 2.40)GHz						
Memory	16248	змв									
System T	ime										
Uptime											
Load Ave	rage 0.00,	0.06, 0.13									

Go to the "Network" page.

Click on "Interfaces" (1) and then click on the "Add Interface" button (2).

The "Add Interface" window will pop up.

In this window select the NIC you wish to configure from the "NIC:" drop down selection box (3).

Give the NIC a name if you wish in the "Interface name:" text box (4).

Do not tick the "DHCP:" tick box (5).

Now assign the static IP address to the NIC in the "IPv4 Address:" text box (6) (in Fester's case this is 192.168.0.5).

Select from the "IPv4 Netmask:" drop down menu (7) the correct value for the subnet mask of your private network (Fester's is 255.255.255.0).

My ISP does not use IPv6 at present so there is nothing to configure for this.

Now scroll down to the bottom of this window and click the "OK" button.

Account System	Tasks Network	Add Interface	<u>@</u>	×	
Global Configuration Int	IPMI Netw	NIC:	igb0 💌 3		
And Include 2		Interface Name:	name of NIC here	4	
NIC	Interface Name	DHCP:	i 5		255
No entry has been found		IPv4 Address:	192.168.0.5	6	Ξ
		IPv4 Netmask:	/24 (255.255.255.0)	7	
		Auto configure IPv6:			I
		IPv6 Address:			
		IPv6 Prefix Length:			
		Options:			
		Alias			
		IPv4 Address:			Ŧ

If you attempt to configure a second NIC with an IP address on the same subnet as the first within the FreeNAS web GUI, you will get an error that looks like this:

2025/07/01 20:50

NIC.

This is because multiple interfaces on the same subnet is an invalid configuration.

Configuring Static IP Addresses Using The FreeNAS Console Setup

Start the IPMI remote console viewer, or connect a keyboard and monitor to your server. You should see a screen similar to this.

```
х
Java iKVM Viewer v1.69.25 [192.168.0.2] TestServer - Resolution 720 X 400 - FPS 35
 Virtual Media
            Record
                   Macro
                          Options
                                        Capture
                                                Power Control
                                 User List
                                                            Exit
1) Configure Network Interfaces
2) Configure Link Aggregation
3) Configure VLAN Interface
4) Configure Default Route
5) Configure Static Routes
6) Configure DNS
   Reset Root Password
7)
8) Reset to factory defaults
9) Shell
10) System Update (requires networking)
11) Create backup
12) Restore from a backup
13) Reboot
14) Shutdown
You may try the following URLs to access the web user interface:
http://192.168.0.58
http://192.168.0.59
http://192.168.0.61
http://192.168.0.62
Enter an option from 1-14:
```

For "Enter an option from 1-14:" enter **1** and press the "Return/Enter" key.



Input the number that corresponds to the NIC you wish to configure in "Select an interface (q to quit):" (1).

Input **n** for "Delete Interface? (y/n):" (2).

Input **n** for "Reset network configuration? (y/n):" (3).

Input **n** for "Configure interface for DHCP? (y/n):" (4).

Input **y** for "Configure IPv4? (y/n):" (5).

Give the NIC a name if you wish at "Interface name:" (6). If you don't want to give it a name then leave it empty and press the "Return/Enter" key.

Type in the static IP address you require at "IPv4 Address:" (7).

Now enter the subnet mask of the private network at "IPv4 Netmask:" (8).

The console should confirm that the configuration has been saved with an "OK".

If you don't need or use IPv6, then just type **n** at "Configure IPv6? (y/n):" (9).



That's the static IP addresses assigned.

From: https://familybrown.org/dokuwiki/ - danb35's Wiki

Permanent link: https://familybrown.org/dokuwiki/doku.php?id=fester:staticip&rev=1465650048

Last update: 2016/06/11 13:00



5/5